QUICKTOOLS FOR THE IBM PC®

USER'S MANUAL

	æ		



User's Manual



LIMITED WARRANTY

Fluke warrants to the original purchaser that the media on which QuickTools is furnished will be free from material defects and workmanship for 90 days from the date of shipment. This warranty does not apply to media which, in Fluke's opinion, have been subject to misuse, alteration, accident or abnormal conditions of operation or handling. Your software program is provided "AS IS" and Fluke does not warrant that it will be error free, operate without interruption or that all errors will be corrected.

For warranty service on your media, contact your nearest Fluke Service Center or send the media with a description of the difficulty, postage prepaid, to the nearest Fluke Service Center. Fluke assumes no risk for damage in transit.

Fluke will replace, free of charge, media which fail to meet this warranty. However, if Fluke determines that the failure was caused by misuse, afteration, accident or abnormal conditions of operation or handling, you will be billed for the replacement. The new media will be sent to you, transportation prepaid. If Fluke is unable, within a reasonable time, to replace your media, your purchase price will be reimbursed to you when you return them to Fluke.

THIS WARRANTY IS EXCLUSIVE AND IS IN LIEU OF ALL OTHER WARRANTIES, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO ANY IMPLIED WARRANTY OF MERCHANTIBILITY OR FITNESS FOR A PARTICULAR PURPOSE OR USE. FLUKE WILL NOT BE LIABLE FOR ANY SPECIAL, INDIRECT, INCIDENTAL, OR CONSEQUENTIAL DAMAGES OR LOSS, INCLUDING LOSS OF DATA, WHETHER IN CONTRACT, TORT, OR OTHERWISE. IF FLUKE IS HELD TO BE LIABLE, FOR ANY REASON, ITS MAXIMUM LIABILITY SHALL NOT EXCEED FIVE TIMES THE PRICE OF THE SOFTWARE.

Table of Contents

SECTION	TITLE	PAGE
1	GETTING STARTED	1-1
	INTRODUCING QUICKTOOLS ABOUT THIS MANUAL You Already Know How This Manual is Organized SYSTEM REQUIREMENTS Hardware Compatibility Setting Things Up INSTALLING QUICKTOOLS ON A HARD DISK GETTING AROUND IN QUICKTOOLS	1-2 1-2 1-3 1-3 1-4 1-5
2	A QUICKTOOLS SESSION	2-1
	STARTING QUICKTOOLS FOR THE FIRST TIME Your Screen Doesn't Look Like This? Set the Communication Parameters What You Have Accomplished START UP THE INTER ACT WINDOW Run a Bus Test Run a Memory Test What You Have Accomplished Run the Same Two Tests, Saving the Interaction Run the Recorded Test Routine Possible Problems WHAT YOU HAVE ACCOMPLISHED	2-3 2-4 2-5 2-7 2-7 2-8 2-8 2-9
3	EDITING STORED COMMANDS	3-1
	STARTING THE EDITOR HOW THE EDITOR WORKS Programmer Comments Operator Messages Adding a Label to a Test Routine Saving a Test Routine WHAT YOU HAVE ACCOMPLISHED	3-3 3-4 3-6 3-6

TABLE OF CONTENTS, continued

SECTION	TITLE	PAGE
4	EXECUTING A QTEST	. 4-1
	ASSIGNING A QTEST TO A FUNCTION KEY USING A QTEST THAT HAS BEEN ASSIGNED Interact and Test Windows Edit Window RUNNING THE ASSIGNED QTEST	. 4-2 . 4-2 . 4-2
5	ENHANCING THE TEST ROUTINE	. 5-1
	THE ON FAIL COMMAND How to Use the ON FAIL Command User-Defined Strings SPEEDING UP TEST EXECUTION QUICKTRACE [™]	. 5-2 . 5-3 . 5-4
6	ON THE MENU	. 6-1
	THE MAIN MENU WINDOW THE EDITOR WINDOW THE INTER ACT WINDOW THE TEST WINDOW	. 6-3 . 6-4
AP PENDIX	GLOSSARY	. A-1

Section 1 Getting Started

INTRODUCING QUICKTOOLS

Quick ToolsTM software makes remote operation of the Fluke 90 μ P Board Tester (the Tester) as easy as using the Tester's front panel. Here are the major features of Quick Tools:

- 1. QuickTools is a communication tool for controlling the Fluke 90 remotely.
 - Records or prints either an entire interaction (commands and responses) between an IBM PC* or a true compatible and the Fluke 90, or just the commands.
 - Assures correct remote command syntax through pop-up prompting.
- 2. QuickTools creates and executes sequences of Fluke 90 commands.
 - Performs user-definable actions on failure.
 - Executes short sequences with function keys.
 - Permits following the execution of command sequences either in full detail, or by observing only the labels of statements as they execute.
 - Includes a built-in program editor featuring pop-up command syntax prompting.

ABOUT THIS MANUAL

Quick Tools software is easy to use because it provides help to new users, but the built-in aids can be turned off later as familiarity increases. The manual has been designed similarly. It is structured as a series of exercises presented in an order most useful to a new user.

You Already Know...

This manual is most effective if you are already familiar with the setup and general operation of the Fluke 90 and the IBM Personal Computer. In particular, you should know how to:

- Locate and connect the serial port
- Plug in and turn on the PC
- Load the operating system (DOS)
- Specify a path and filename (e.g., C:\QKTLS\qt.exe)
- Specify a pattern for matching (e.g., DIR A:*.TST)
- Change the active drive
- Start up an application program
- Use an editor program to add information to a file

You should also be able to use these DOS commands effectively:

MKDIR	(make directory, e.g., MKDIR C:\QKTLS)
DIR	(show directory listing)
COPY	(copy a file, e.g., COPY A:*.* C:\QKTLS)
CD	(change working directory, e.g., CD C:\QKTLS)

You may need to refer to the appropriate sections of your computer's operation manual if you are unsure about how to use these commands.

How This Manual is Organized

The QuickTools manual is arranged as a group of tasks, presented in the order that most new users need to perform them.

Section !	is an introduction to the QuickTools software and this manual, and shows how to connect the PC, Fluke 90 Tester, and your UUT in preparation for testing.
Section 2	takes you through a practice Quick Tools session in which you begin developing a test program for your own UUT.
Section 3	continues the development of the test routine while explaining how to use the QuickTools editor.
Section 4	explains how to run the test routine that is being developed.
Section 5	adds some enhancements to the test routine and shows how to include some sophisticated features.
Section 6	is a reference to all the QuickTools menus.

SYSTEM REQUIREMENTS

Quick Tools software is designed to run on the IBM PC, PC-XT, and PC-AT or compatibles. The software runs on systems under DOS version 2.1 or later. If you have an earlier version of DOS, you must update it before attempting to run Quick Tools.

Hardware Compatibility

If you intend to use a system other than an IBM personal computer for running QuickTools, the computer must meet certain criteria to be truly hardware compatible.

1. Quick Tools communication drivers communicate directly with two components at the serial port:

Intel* 8259A Programmable Interrupt Controller National Semiconductor* 8250 or 16450 UART

All IBM systems and most compatibles use these parts, but if your compatible does not, Quick Tools may not communicate properly.

2. QuickTools screen drivers directly address the following standard IBM (or compatible) display boards:

Standard monochrome display Enhanced Graphics Adapter (EGA) Color Graphics Adapter (CGA) Video Graphics Array (VGA)

If your system is compatible as described here, skip to the next section, titled "Setting Things Up."

3. However, QuickTools provides an alternative screen output that does not directly access the display board. Instead, the alternative output uses MS-DOS ANSI.SYS drivers. To make use of the alternative screen output requires you to install device drivers on the bootup disk. Include the following line in the file CONFIG.SYS:

DEVICE=ANSI.SYS

If ANSI.SYS was not specified in CONFIG.SYS at bootup, reboot so the PC will load the ANSI console driver.

Setting Things Up

1. Make a backup copy of the QuickTools disk and put the original away for safekeeping. Use the copy for day-to-day operations.

CAUTION

Memory Resident programs may cause a loss of serial data when running QuickTools. Your autoexec.bat file may be executing a program that stays active after returning automatically to DOS. It may be necessary to edit or remove the autoexec.bat file and reboot.

- 2. Connect the IBM PC serial port (RS-232) to the Fluke 90.
- 3. Connect the Fluke 90 to a known good Unit Under Test (UUT). Do not connect a defective UUT until you are familiar with the way Quick Tools works. Refer to the Fluke 90 Operator's Manual if you do not know how to make this connection.

The cable provided with your Fluke 90 fits most 25-pin IBM serial port connectors, but if you need an adapter, consult your local Fluke representative. You can perform most QuickTools operations even without the adapter, but the practice session in Section 2 assumes that the PC and the Tester are connected and that a working UUT is connected for testing.




Figure 1. Connections Between IBM PC, Fluke 90 µP Board Tester and UUT

INSTALLING QUICKTOOLS ON A HARD DISK

If you have a hard disk, you can install QuickTools there to take advantage of its speed and convenience.

- 1. Change the default drive to the hard disk.
- 2. Make a directory using the DOS command MKDIR QKTLS.
- 3. Insert the QuickTools floppy disk and copy all files to the new hard disk directory. Assuming the floppy drive is drive A: and the hard drive is C:, the copy command would be:

COPY A:*.* C:\QKTLS

GETTING AROUND IN QUICKTOOLS

QuickTools is easy to learn and to use. All operations are selected from menus.

To select a menu item from the Main Menu:

Simultaneously press (Alt) and the keythat corresponds to the upper case letter in the selection. For example, to select Setup, press (Alt) s.

To select a menu item within Submenus:

Move the current selection using the arrow keys ($\uparrow \downarrow$), then press the Enter key. (The Enter key is shown in this manual as \longleftarrow .)

OR

Press the key that corresponds to the upper case letter in the selection. For example, to select Warning beeper from the Setup menu, press w.

Entry Fields:

Filenames and other editable selections are displayed in reverse video to indicate that they can be modified. Use the following keys when working with entry fields:

(INSERT) toggles between Insert and Typeover modes.

(DELETE) deletes the character at the cursor position.

(BACKSPACE) deletes the character to the left of the cursor position.

(CTRL) (END) deletes all of the field to the right of the cursor.

← and → move the cursor a character at a time within the field.

(HOME) moves the cursor all the way to the left end of the field.

(END) moves the cursor all the way to the right end of the field.

	*		
ė.			

Section 2 A QuickTools Session

The session described here gets Quick Tools operating right away and introduces you to most of its features.

STARTING QUICKTOOLS FOR THE FIRST TIME

Boot DOS. Insert the QuickTools floppy disk, and change the default drive to the one where QuickTools is loaded. To start QuickTools, type:

If you are using the ANSI drivers, start QuickTools by typing:

When you start QuickTools, the Main Menu appears on the display. Each time you start QuickTools, the message " $\langle Alt \rangle$ H for Help" is flashing in the lower right corner. Try it. After reading the help screen, return to the main menu by pressing $\langle Alt \rangle$ x.




Figure 2. QuickTools Main Menu

Your Screen Doesn't Look Like This?

If you do not see the display shown in Figure 2, make sure that you have done the following:

- Correctly loaded DOS Version 2.1 or later
- Used the correct command to start up QuickTools: QT

OR

- For the alternate display mode, started QuickTools using QT-A
- If necessary, placed the ANSI.SYS device driver on the same disk as DOS. This must be the ANSI.SYS that was supplied with your system disk.
- Booted the system with the CONFIG.SYS file specifying DEVICE = ANSI.SYS

Until QuickTools is running, any error messages come from the operating system. If DOS reports no errors, but you don't see the screen shown here, check out these possibilities:

- Odd characters seem to be filling the screen
 - There is a problem with the ANSI.SYS driver. Be sure you have correctly configured the disk.
- The screen has little contrast or appears blurry.

Some monochrome PC's may display color poorly. Go to the Setup Menu (Alt s), press the C key (color), then press the A key (all areas of the screen to monochrome). Press (Alt) x to go back to the Main Menu.

If all these things are correct, you may have a defective disk. In this case, make another QuickTools backup disk and try again.

To exit from QuickTools, press (Alt) x from the Main Menu.

SET THE COMMUNICATION PARAMETERS

At the Main Menu, press (Alt) s.




Figure 3. Setup Menu

Use the following steps to set up the Fluke 90 port.

- 1. If the Fluke 90 port selection is already highlighted, you can just press is not highlighted, either use the arrow keys to move there, then press , or press the f key (Fluke 90 port).
- Press either 1 or 2, depending on whether the Fluke 90 is connected to COM1 or COM2.
- 3. Press 8 to select 8 data bits.
- 4. Press 9 to select 9600 baud and return to the Setup Menu.

What You Have Accomplished

By making the Fluke 90 selection from the Setup Menu, you have defined the communication link between the Tester and the PC.

•n power up, the Fluke 90 sets itself to communicate using eight data bits and 1200 baud. Serial communication requires both devices to be set the same, so QuickTools automatically sets both the PC and the Fluke 90 to the selected parameters. For example, you may prefer to operate at a higher speed. Doing so only requires that you change the baud rates election in the Setup Menu.

QuickTools first establishes communication with the Tester, resets its communication parameters, then resets the PC to match.

START UP THE INTERACT WINDOW

The Interact Window provides one of the most powerful features of QuickTools: a way to send remote commands to the Tester and immediately see the results. An interact session is usually the first step in test routine development because it interactively tests the UUT. Later the commands are combined into a test routine.

To exit the Setup Menu, press:

```
⟨Alt⟩ x to return to the Main Menu, or, 
⟨Alt⟩ i ← to go immediately to the Interact Window
```

Before it starts an interactive session, QuickTools first displays the name of the default Program File, the one that QuickTools will load and prepare to run in the Interact session. Brand new copies of QuickTools uses an empty file called DUMMY.UUT as the name of the default Program File.




Figure 4. Interact Window Showing the Default Program Name

Pressing \triangleleft activates the Interact window and establishes a communication link between the PC and the Fluke 90. The screen should look like the next illustration.




Figure 5. The Interact Window

Run a Bus Test

Whenever the Tester is ready to accept a command, the remote command prompt ENTER's appears on the bottom line of the PC display.

Run Test Bus by typing:

⟨Alt⟩b to display bus tests, ← to select test bus.

Observe the display. QuickTools has generated the remote command syntax for a Test Bus (BT) and sent it to the Fluke 90. While QuickTools is waiting for the Tester's response, the command line displays

...working... ALT_C to cancel.

Run a Memory Test

Type (Alt) m. Notice that the QuickTools command prompting display changes to show the available memory tests.




Figure 6. Memory Tests

Use the following steps to run a memory test.

- 2. QuickTools prompts for a beginning address. To begin the test at the displayed address, just press \(\bigcup \). To change the address, press \(\bigcup HOME \rangle \) to go to the left, then delete the old address by pressing \(\cap CTRL \rangle \) \(\bigcup END \rangle \). Type in the lowest RAM address of your UUT. When the address is correct, press \(\bigcup \).
- 3. Quick Tools now prompts for an ending address and supplies 00FF, the default. This time to change the address, just type the new address. The editor always starts in typeover mode.
- 4. To send the command, press ← . Observe the display. The return of the ENTER) prompt indicates that the Tester is ready for the next command. To send the command again, press † then ← . To change the command, press †, then edit the line before pressing ← .
- 5. Run the same test a few times, trying out different address ranges. If the ending address is lower than the beginning address, the tester responds with ????, indicating it is unable to complete the command.

Each command is redisplayed above the ENTER line. The buffer you are seeing can be printed out, saved on the disk, or edited.

What You Have Accomplished

The Interact Window opens communication with the Fluke 90 and sends remote commands to it. In these few minutes, you have already used QuickTools' powerful command syntax generator. You never need to remember the name or syntax of Fluke 90 commands, because QuickTools takes care of that for you.

When you changed the beginning address, you used the QuickTools editor for the first time. The editor's capabilities are fully explained in Section 3.

By sending the BT and MT commands, you have checked the UUT bus and the RAM address range you entered.

Run the Same Two Tests, Saving the Interaction

To prepare to save the interaction:

- 1. Select Save from the Interact menu.
- 2. Select disk On.
- 3. Select commands Only. You will be asked to name the Recording file.
- 4. For now, name the new file something easy to remember, like MYTEST.IST. If the file you name already exists, a message appears stating that the commands you enter will be appended to the existing file.

CAUTION

QuickTools reserves two filenames for its own use:

INIT_QT VAL
TEMP_QT DIR

The INIT_QT file stores values that QuickTools uses from one session to the next, like the screen colors and default filenames. The TEMP_QT directory is a temporary file created and deleted during QuickTools operation.

Now, repeat the Bus Test and Memory Test that you performed earlier in this section. The commands you send to the Tester are logged to the file named MYTEST.1ST.

Stop recording by selecting Save, then Disk off. (Leaving the Interact Window automatically closes the disk file for you.)

If you selected "Complete Data" in step 3 above, the responses would also be recorded. However, in this case, the file could not be Run until the responses were edited out.

Run the Recorded Test Routine

Once the test routine has been recorded to disk, it is always available for execution. Run the test routine you have just saved.

- 1. While you are still in the Interact Window, select beGin. QuickTools asks for a file name to begin running, showing the last named Program file. Change it to MYTEST. IST.
- 2. Press \(\bigs_{\text{--}}^{\text{--}}\) to run the test named in the pop-up window. Observe the display. As the tests run, the commands are displayed as they are sent, alternating with the Tester's responses. A message window indicates QuickTools program activity. QuickTools displays two messages, first:

Loading MYTEST.1ST

and finally:

Program complete

3. Leave the Interact Window by pressing (Alt) x. QuickTools asks for confirmation because exiting clears the transaction records.

Possible Problems

If something didn't work correctly when you ran the new test routine, it may actually indicate normal operation! The Tester attempts to interpret everything QuickTools sends as a remote command. Check for the following possible problems:

- If the tester doesn't recognize a line as a valid Fluke 90 remote command, it returns ????. Look for typographical errors.
- If you selected "Complete Data" and saved both the remote commands and the Tester's responses, there will be many instances of the Tester returning ????. To avoid this, be sure to save commands only or edit out the responses. The next section explains how to use the editor.

 Memory Resident programs may cause a loss of serial data when running QuickTools. Your autoexec.bat file may be executing a program that stays active after returning automatically to DOS. It may be necessary to edit or remove the autoexec.bat file and reboot.

WHAT YOU HAVE ACCOMPLISHED

In this section, you have performed most of the tasks needed to create a new test routine for your own UUT. In this first QuickTools session you have done the following:

- Established communication between the PC and the Tester.
- Used QuickTools remote command syntax prompting as an aid to sending commands to the Tester.
- Saved the commands to a new file.
- Run the newly recorded test routine.

In the next section, you will edit the saved interaction to begin creating a fully developed test program.

Section 3 **Editing Stored Commands**

Any series of stored remote commands can be called a test routine, because without further enhancement they perform a series of tests on the UUT. Editing a test routine can make it even more useful. This section explains how to use Quick Tools built-in editor to add capabilities to the test routine. Further enhancements are covered in the last section.

NOTE

Any text editing program can be used to create or edit test routines as long as the editor can save the results as an ASCII text file.

START THE EDITOR

From the Main Menu, press (Alt) e then \leftarrow to start the editor program. Your display should appear as shown in the following figure.

Like the Interact window, the editor also uses key-prompting to generate the proper Fluke 90 remote command syntax.




Figure 7. The Editor Window

HOW THE EDITOR WORKS

The QuickTools Editor is line-oriented. Each line is a single complete Fluke 90 or QuickTools command. Table 1 shows the functions of all the editing keys.

Table 1. QuickTools Editor Key Functions

KEY	toggles between insert and typeover modes			
(INSERT)				
₽.	the ENTER key breaks the line at the cursor. Everything to the right of the cursor forms a new line. If you press ENTER at the end of the line, a blank line is created, ready for entering a new command.			
	CURSOR MOVEMENT KEYS			
→	moves the cursor to the right one character position			
-	moves the cursor to the left one character			
t	moves the cursor up one line			
ļ	moves the cursor down one line			
(PAGE UP)	moves the cursor up in the buffer by one full page			
(PAGE DOWN)	moves the cursor down in the the buffer by one full page			
⟨End⟩	moves the cursor to the right end of the line			
⟨Home⟩	moves the cursor to the left end of the line			
	DELETION KEYS			
⟨DEL⟩	deletes the character at the cursor position			
(Ctrl) (End)	deletes from the cursor to the right end of the line			
〈Back Space〉	deletes the character to the left of the cursor. If pressed when the cursor is at the left margin, Back Space combines the line with the line directly above it.			

Programmer Comments

To add a programmer comment to a test routine, precede the comment with two exclamation points:

!!Programmer comments do not display while the program is running

QuickTools treats programmer comments in a traditional way. Everything to the right of the comment marker (!!) is ignored at runtime.

NOTE

If you forget to include the "!!" in a comment line, Quick Tools sends the line as a command. Generally the response from the Tester will be ????.

Operator Messages

A single exclamation point introduces an operator message. These messages can be displayed, recorded, or printed, but they are never output to the Fluke 90. Use operator messages to check on the progress of the test routine or to give directions to the operator.

!RAMTEST IN PROGRESS 0000 - 00FF

Adding a Label to a Test Routine

Labels have two uses:

- 1. They display in the Test window, providing a convenient way for an operator to follow the execution of the test routine.
- 2. They identify a part of a test routine for branching. This usage is discussed in detail in Section 5.

A label can be up to 78 characters long and ends with a colon character (:). Fluke 90 remote commands follow the label. For example, part of the MYTES.T.IST routine might be labeled as follows:

MemCheck1: MT 0201 03FF

NOTE

Quick Tools deletes leading and trailing spaces, so the following labels are equivalent:

mem check 1: mem check 1: MEM check 1:

Labels display on the PC in the Test window, but not the Interact window.

NOTE

A label can be made invisible by ending it with two colon characters. Use invisible labels to suppress the display of less important labels that a test may branch to.

Use the editor to add programmer's comments, operator messages, additional Fluke 90 commands, and labels to the test routine you are developing. A final version of MYTEST. IST might look like this:




Figure 8. Sample Program with Comments and Messages

Saving a Test Routine

Before exiting the editor, save the test routine. Select "fileS" from the menu bar, then select "Save file". You will be asked to name the file to save. If you use the name MYT EST.1ST, QuickTools overwrites the old file.

WHAT YOU HAVE ACCOMPLISHED

The main purpose of this section has been to introduce QuickTools built-in editor, and show you how to use it to move around in and edit a QuickTools test routine. In Section 3 you you have accomplished the following:

- Added comments, messages, and labels to the test routine.
- Saved the test routine to a disk file.

Section 4 Executing a Qtest

In Section 2 you created a test program and executed it in the Interact Window. Section 3 expanded the test program to include labels, operator messages and programmer comments. The purpose of this section is to explore QuickTools execution of these Qtest features.

ASSIGNING A QTEST TO A FUNCTION KEY

When MYTEST. IST is fully developed and proven to locate faults reliably, you may want to speed things up by assigning it to a function key so the tests can be run by pressing just one key.

To assign a Qtest to a function key, perform the following steps.

- I. Return to the Main Menu.
- 2. Select Assign, and press the Function Key you wish to use for the Qtest.
- 3. A Status Window appears that displays the current information for the Function Key you pressed. The selection "to Qtest" is highlighted. Press .
- 4. An entry box appears, asking you for the name of the Qtest. Type MYTEST.IST

 When assigning tests to a Function Key, be sure to indicate the entire path.

 The full specification of a file can be up to 42 characters.
- 5. Next, another entry box requests a label for the file. The label can be a maximum of six characters. This label appears on the "Show F-Key" popup. Enter MY1ST
- 6. QuickTools next asks for a description of the file. The description can be a maximum of of 22 characters and it appears in the Status Window area on the Main Menu when you select Assign, then F-Key. The description supplies the operator with additional information about the Qtest. After entering a description, press
- 7. To check that everything has been keyed in properly, repeat step 2. Press (ESC) to leave the entry unchanged.

USING A QTEST THAT HAS BEEN ASSIGNED

Assigning a Qtest to a Function Key saves time and effort because all the tests are available with a single keystroke. The assigned Qtest can be used in the Interact, Test, and Edit Windows.

Interact and Test Windows

In the Interact and Test Windows, to run the tests that make up a Qtest, press only the Function Key that has the Qtest assigned to it. This can be an efficient way to prescreen boards. For example, a function key might be assigned to a Qtest that runs a Bus Test and some preliminary checksum tests. Another use of an assigned Qtest in the Interact Window might be to run a thorough set of memory tests on an area of memory already identified as faulty.

Pressing an assigned Function key is equivalent to pressing (Alt) g(beGin), S(Start), entering a filename, and

Edit Window

In the Edit Window, pressing an assigned Function Key inserts the tests that make up the Qtest into the buffer. This is a way to include subtests into a group of longer tests (which in turn might be assigned to a Function Key).

In the Edit Window, pressing and assigned Function key is equivalent to pressing (Alt) s (fileS), I (Insert), entering a filename and \blacktriangleleft .

Unless you later change an F-key assignment with the Assign function, the key will always run the tests in the file you've named. QuickTools retains Function key assignments between sessions. Remember that if you delete, rename, or move a file assigned to a function key, QuickTools will not be able to locate it.

RUNNING THE ASSIGNED QTEST

Once a test has been assigned to a Function key, it is available by pressing just that Function key. To try it out the first time, follow these steps:

- 1. From the Main Menu, press (Alt) i and \leftarrow to go to the Interact window.
- 2. Press (Alt) f (showF-keys). Toggle the Function key display to ON by pressing

 Confirm that you have assigned MYIST and verify the function key assignment.
- 3. Press the Function key indicated. Note that MYTEST. IST executes just as it has done in previous excercises (Section 2). All operator messages should appear, but you should see none of the programmer comments or labels.
- 4. Exit the Interact window.

5. Go to the Test screen (⟨Alt⟩ t and ←) and observe the display. The choices on the screen are described in Figure 9.




Figure 9. Running the Test Routine

6. Again press the Function key assigned to MYTEST.IST. Observe the display. As MYTEST.IST is running, each label appears, followed by the word PASS or FALL. If the UUT is operating properly, the screen will look as follows:




Figure 10. Labels and Pass/Fail Indications for MYTEST.1ST

7. To exit Test mode, press (Alt) x. As usual, QuickTools requests confirmation.

Section 5 Enhancing the Test Routine

This section adds some sophisticated features to the test routine you have been developing. It explains how to set up branching within the routine and how to call another test routine based on UUT failure conditions.

THE ON FAIL COMMAND

When QuickTools is executing a test program, it sends each Fluke 90 command in sequence until a failure occurs. A failure is recognized as one of three conditions:

1. The Tester returns the string FAIL.

If QuickTools receives the word FAIL from the Tester, it means that the UUT has failed a test called for by a remote command.

2. The Tester returns the string ????.

If the Tester sends ????, it means that it was unable to recognize the command, indicating the command had a syntax error.

3. The Tester returns a string different from one specified in an ON FAIL statement. User-defined strings are explained later in this section.

When a failure is detected, Quick Tools takes the action specified by the most recent ON FAIL command. ON FAIL can specify one of these actions:

PAUSE (the default action)

BRANCH.. to a label within the same test routine

CALL .. another test routine and returns upon completion

NO ACTION disables all failure action

The specified action remains in effect until changed by a different ON FAIL command or until a failure action is taken. When QuickTools takes action on a failure (PAUSE, BRANCH to a label, or CALL a different program), it automatically resets the failure activity to PAUSE, cancelling the currently defined action and any user-defined string.

How to Use the ON FAIL Command

The following examples illustrate how to use the ON FAIL command in various ways:

Example 1:

ON FAIL PAUSE

The ON FAIL PAUSE command halts test program execution on a failure. This is the default condition, and is asssumed at the beginning of a test program.

Example 2:

ON FAIL BRANCH {label}

The ON FAIL BRANCH comand causes the test routine to begin execution at the indicated label if the test fails. For example, the following commands tell QuickTools to branch to the line labeled DAG: if any failures occur. If there are no failures, everything proceeds sequentially to the END statement.

```
ON FAIL BRANCH DAG
BT

more command lines

END !! normal program execution stops here
DAG: !beGin MYTEST.2ND when ready
```

Example 3:

ON FAIL CALL (program)

The ON FAIL CALL command causes the test routine to pass control to another test routine. When the called routine is complete, control returns to the initial routine.

For example, the following commands first perform a memory test. If there is a failure, the test routine MYTEST.2ND will execute. When MYTEST.2ND completes, control returns to the first test routine, which then performs a CHECKSUM test.

If the memory test does not fail, the next command (CK 0000 0100) executes.

ON FAIL CALL MYTEST.2ND MT 8000 8080 CK 0000 0100

User-Defined Strings

In all of the preceding examples, a "failure" may be an actual UUT failure (FAIL) or a syntax error (????). Failures also occur if the response from the tester does not contain the user-defined string.

Use the following syntax to construct valid commands containing strings for matching:

Example:

The following list of commands tells the Tester to call the program 'F90RT' if the checksum returned from the Fluke 90 is not the same as the checksum listed in the ON FAIL command. If "E720" is contained anywhere in the returned string, the program continues.

```
ON FAIL (E720) CALL F90_RT
CK 0000 00FF
ON FAIL (4F36) CALL F90_RT
CK 0101 0200
ON FAIL PAUSE !! cancels user-defined string, specifies new action
more command lines
```

NOTE

The maximum length of an ON FAIL (string) command is 78 characters.

SPEEDING UP TEST EXECUTION

The next few paragraphs describe a method for speeding up test routine execution.

In operation, the Fluke 90 Board Tester "cycle steals" from the UUT microprocessor. This means that normally the Fluke 90 does all of its testing while the UUT processor is running. By having the test routine halt the UUT processor, considerable time can be gained since the Testerdoes not have to wait for a free processor cycle before performing its activity in the UUT.

In the following example program listing, a speed increase of 4 to 1 is accomplished by using a breakpoint to halt the microprocessor during testing.

CAUTION

The method described here should only be used for UUTs with static RAM because the refresh cycle may be stopped during breakpoint operation. Stopping a UUT with dynamic RAM may cause the contents of the RAM to be lost.

Example Program:

```
Example of speed increases available for STATIC RAM boards bt db Cycle sharing timing test:
!! For this portion of the tests, the UUT is running.
!! execution time for this memory test is about 21 seconds !! for checksum, about 12 seconds.
! Time the execution of the following two tests.
MT 8000 9000 ck 0000 1000
!! record execution time
!! now we'll halt the UUT and retest !! time for the memory test is now about 7 seconds, !! for the ROM checksum test, 3 seconds
UUT Halted timing test:
bp
AX
! Time the two tests again mt 8000 9000 ck 0000 1000
! record execution time db end
```

QUICKTRACET*

The QuickTraceTM function follows and isolates suspected faulty address, data, or control lines on the UUT. The signal line can be followed to isolate the fault. When QuickTrace is used in a test program, The program halts and allows you to probe various points on the UUT. Each time you probe a trace on the UUT, the trace name is displayed on the QuickTools screen (followed by a carriage return). If two traces are shorted together, both trace names are displayed on the same line of the QuickTools screen. To exit from QuickTrace, either press (Alt) c on the IBM PC keyboard or press the button on the probe.

Section 6 On the Menu

THE MAIN MENU WINDOW

Assign f-key

QuickTools uses (Alt) h for Help and (Alt) x for Exit. The Assign f-key selection lets you place these on function keys of your choice and also assigns function keys to often-used sequences of Fluke 90 commands (Qtests). An option lets you match the format of a function key reminder display to the physical arrangement of your keyboard.

Horizontal Form Vertical Form Matches the Function Key reminder display to the layout of the keyboard being used.

press (FI) - (FIO)

Changes the assignment of a Function Key.

Disk

A gateway to the Disk Operating System. This menu permits copying, deleting, printing, and viewing files without leaving OuickTools.

select File(s)

Marks files for deletion, copying, printing or viewing. QuickTools prompts for a pattern and will accept wildcards. Files matching the pattern display in the menu area.

When you press at a highlighted filename, QuickTools marks the file with an asterisk. (Alt) x ends file selection and returns you to the Disk menu to choose the operation for the selected files.

Delete

Deletes all marked files after confirmation.

Copy

Copies the marked file(s). QuickTools prompts for a destination filename. When the destination is a directory, all selected files are copied there without a name change. In any copy operation, a destination file with the same name as the source file is overwritten without warning.

Print Sends the selected file(s) to the printer port.

View Displays the selected file(s).

Setup Changes the parameters that control communication between Quick Tools and the Fluke 90, enables and disables the warning beeper, determines the colors used by Quick Tools screens, and

establishes the default files that QuickTools uses for testing and

recording.

Fluke 90 port Sets the port (COM1 or COM2), baud rate,

and number of databits to be used for commun-

ication between the PC and the Fluke 90.

Printer port Selects the printer port QuickTools uses.

Warning Beeper Enables and disables operation of the PC

beeper.

Color Selection Sets the background colors for the menu bar,

main screen body and status/entry line. Quick-Tools automatically changes the foreground colors. For best results with monochrome monitors, choose "All" to select monochrome

for all three areas.

Default files Tells Ouick Tools software the names of the files

to use for running (the default Program File), for recording (the default Recording File), and for the Upload and Download filenames.

Editor Accesses QuickTools text editor for creating and modifying

test routines.

Interact Window is like a super terminal emulator. Fluke

90 commands can be entered directly or by way of QuickTools unique command prompting. The entire interaction can be logged to disk for later editing or to a printer for analysis. One option limits the storage to commands only, as a way to quickly create test programs. The last 100 transactions of an

Interact session are available for screen reviewing.

Test The Test Window offers the quickest way to execute stored test

programs. Rather than displaying the full command and response activity of the program, Test displays only operator messages, program labels, and the pass/fail results of the

tests.

THE EDITOR WINDOW

priNt Selects printing. This selection permits you to print out the

current program file.

showF-keys Displays a reminder of the Function Key assignments. The

reminder display disappears at the next keystroke.

Pressing an F-key assigned to a test program causes that

program to be inserted below the current line.

promptKey Displays a representation of the Fluke 90 front panel. This

reminder display persists until you turn it off by selecting it a

second time.

Save Allows recording the current session to disk, removing the

current session and loading a new file from disk, and inserting a file from disk into the current session (the file is added below

the current cursor position in the Editor Window).

Verify Duringeditor operation, single lines can be sent to the Tester to

verify the command. Move the highlighted lineusing the arrow keys, then select Verify to send the command line to the Tester.

Results are displayed on the bottom line.

eXit Leaves the editor, after asking for confirmation. If the file has

changed since the last save, prompts again to exit without

saving.

THE INTERACT WINDOW

priNt Selects printing. This selection permits you to send the Interact

session to the printer.

showF-keys Displays a reminder of the Function Key assignments. The

reminder display disappears at the next keystroke.

promptKey Shows the ALT keys to use for invoking Fluke 90 command

syntax. This reminder display persists until you turn it off by

selecting prompt-Key a second time.

Save Allows logging the current session. The session is saved to the

currently named Recording file, which can be changed here or in the Setup Menu. In Interact, you can save the entire transaction or just the commands. You can log the interactions as they occur, or log the contents of the current 100-line buffer.

beGin Starts, pauses, and continues the current Program File, which

can be changed either here or in the Setup Menu. Quick Tools displays all commands and operator messages and the the Fluke 90 responses. To limit the display to labels, operator messages, and pass/fail responses only, use the Test Window.

eXit Leaves the session, but first asks for confirmation to ensure

that any changed or new files have been logged. Leaving clears

the transaction buffer.

THE TEST WINDOW

priNt Selects printing. This selection permits you to send the Test

session to the printer.

showF-keys Displays a reminder of the Function Key assignments. The

reminder display disappears at the next keystroke. Pressing an F-key assigned to a test program causes that program to

execute immediately.

Save Allows logging the current session. The session is saved to the

currently named Recording file, which can be changed here or

in the Setup Menu.

beGin Starts, pauses, and continues the current Program File. As the

program executes, only labels, pass/fail responses, and operator comments display. To see all commands and their responses,

use the Interact window's beGin selection.

eXit Leaves the Test window, but first asks for confirmation.

Appendix A Glossary

interaction

A communication between the PC and the Tester. Interactions have two parts: first, QuickTools sends a remote command from the IBM PC to the Tester. In the second part, the Tester responds. The response might be test results, a checksum calculated for an area of memory, an address or data line being probed using QuickTrace, and so on.

message area

An area in the QuickTools display that gives information about different operations. For example, in the Test and Interact Windows, Qtest progress is shown in this area.

program file

A disk file containing a series of Fluke 90 commands. QuickTools permits program files to be edited, assigned to function keys, run, or printed out.

Qtest

A sequence of Fluke 90 commands. Also called a test routine or a program, a Qtest is a program file that is assigned to a function key. Qtests are assigned from the Main Menu and executed in the Interact and Test Windows. In the Editor, pressing a Function key which has a Qtest assigned inserts the Qtest into a program.

recording file

The file QuickTools uses to save interactions.

select

To make a choice from a menu. The selected item is highlighted and preceded by a prompt symbol >.

Sclect Menu options by pressing (Alt) and the capitalized letter. Submenus require only the capitalized letter. For example, in the Setup Menu, press W to select Warning beeper, then N to select oN.

status/entry line

QuickTools uses the bottom line of each window to display information pertinent to that window's operation. For example, in the Editor Window, the bottom line of the display expands the syntax of the currently selected command line.